

How to Check CPU Temperature on Linux

Link: <https://phoenixnap.com/kb/linux-cpu-temp>

Introduction

Like any electrical component, [CPUs](#) generate heat when being used. Some resource-demanding programs cause the CPU to increase the clock speed, which results in higher temperatures. Dust buildup also causes the CPU to overheat.

High temperatures shorten the lifespan of sensitive components, so keeping track of CPU temperatures is crucial. This way, you prevent performance throttling or component damage.

In this tutorial, you will learn how to use different tools and in-built utilities to check CPU temperature on Linux machines.

Prerequisites

- A machine running Linux
- An account with sudo/root privileges

Check CPU Temperature Using Lm-Sensors

Lm-sensors is a command-line utility for [hardware](#) monitoring. Use the tool to check the temperature of the CPU and other components. Follow these steps to install and configure Lm-sensors:

1. Open the terminal and install these packages using a package manager for your distribution. In Ubuntu, use the following command:

```
sudo apt install hddtemp lm-sensors
```

Wait for the **lm-sensors** and **hddtemp** to finish downloading and installing.

2. Execute the `sensors` command to see the CPU temperature. The output shows the current temperature readings of all sensors in the machine. The results include the temperature of each core and maximum thresholds.

Sensors command output on Linux Ubuntu.

3. To check SSD and hard drive temperatures, execute the following command:

```
sudo hddtemp /dev/sda
```

Check hard drive temperature on Linux Ubuntu.

The output shows the temperature of the selected disk.

4. To see which system components you can monitor, run `sudo sensors-detect`.

Answer **YES** to multiple scanning requests until the system scan is complete.

Output showing a summary of sensors detected on Ubuntu.

When the scan completes, the output shows the summary.

5. To ensure that system monitoring works, load the needed modules using the following command:

```
/etc/init.d/kmod start
```

Start kmod service on Ubuntu to monitor hardware temperature.

6. To run the `sensors` command repeatedly and get real-time data in the terminal, execute the following command:

```
watch sensors
```

Real-time output in terminal showing CPU temperature on Ubuntu.

The output refreshes every two seconds and displays the current CPU temperature reading.

Note: To check CPU usage on Linux, read our tutorial on [How to check CPU usage](#).

Check CPU Temperature Using Psensor

Psensor is a **GUI app** that allows you to monitor the temperature of various system components. This utility also allows you to monitor CPU usage and fan speed.

Psensor includes an [applet](#) indicator for Ubuntu, allowing you to display the temperature in the top panel to notify you when the temperatures get too high.

Install Psensor

Before installing Psensor, you need to install and configure Lm-sensors.

1. Run this command to install the necessary packages:

```
sudo apt install lm-sensors hddtemp
```

2. Next, scan for sensors in your machine:

```
sudo sensors-detect
```

Answer **YES** to any scan requests until the scan is completed.

3. To make sure the packages are installed, execute the `sensors` command.

Sensors command output on Linux Ubuntu.

4. Update the package repository with `sudo apt update`.

5. Install Psensor using the following command:

```
sudo apt install psensor
```

Install Psensor app on Ubuntu Linux.

Answer **YES** and wait for the installation to finish.

Using Psensor

Search for **Psensor** in the app menu and open the utility. The app displays a graph of the selected values and shows the CPU temperature, CPU and memory usage, free RAM, GPU temperature, and [HDD](#) temperature.

Psensor app on Ubuntu showing hardware temperatures.

To configure Psensor and set which stats you want to see, follow these steps:

1. Click **Psensor** in the menu bar, followed by **Preferences**.

2. Check off the boxes for the options you want – whether Psensor launches on system startup, the update interval, graph colors, etc.

Psensor app Preferences on Ubuntu Linux.

3. To show CPU or HDD temperatures in the top panel, go to **Sensor Preferences** under the **Application Indicator**. Enable the **Display sensor in the label** option.

Display sensor output in the top label in Ubuntu.

Note: Learn more about monitoring CPU performance by referring to our article on [Linux perf](#), a lightweight command-line utility.

Check Temperature Without Third-Party Utilities

There is a way to use the in-built utilities to check the CPU temperature if you don't want to use third-party apps.

1. To check the CPU temperature without installing a third-party app, use the following command:

```
cat /sys/class/thermal/thermal_zone*/temp
```

Display CPU temperature in Ubuntu without third-party apps.

The output shows the CPU temperature in the five-digit format. Here, 49000 means 49C.

2. If you get several thermal zones and different temperatures, execute the following command to see what a single thermal zone represents:

```
cat /sys/class/thermal/<thermal_zoneNumber>/type
```

For example, run `cat /sys/class/thermal/thermal_zone2/type` to see the type of thermal zone 2.

The CPU temperature is in the zone labeled **x86_pkg_temp**.

3. To see what all the thermal zones are referring to, use:

```
paste <(cat /sys/class/thermal/thermal_zone*/type) <(cat /sys/class/thermal/thermal_zone*/temp) | column -s '\t' -t | sed 's/\(.\)\..$/.\1°C/'
```

Display CPU temperature in Ubuntu without third-party apps.

The output shows the last stored temperature for that thermal zone in degrees Celsius. In this example, there is only one thermal zone, labeled **x86_pkg_temp**, which represents the CPU temperature.

Conclusion

You now know how to check CPU temperature on Linux using various utilities. The guide also showed how to configure the tools to display other information, such as GPU and HDD temperature.

Next you should read

[Bare Metal Servers SysAdmin](#)

[How to Install IPMItool on Centos 7/8 & Ubuntu 18.04/20.04](#)

August 27, 2020

This article helps you install IPMItool on your CentOS or Ubuntu system. Download, install and enable...

[READ MORE](#)

[DevOps and Development Virtualization](#)

[How to Set Docker Memory and CPU Usage Limit](#)

December 6, 2023

Docker containers have unlimited access to RAM and CPU memory of the host. This is not the recommended...

[READ MORE](#)

[SysAdmin Web Servers](#)

[How to Check Memory Usage in Linux, 5 Simple Commands](#)

March 28, 2024

In this tutorial, learn the five most commonly used commands to check memory usage in Linux...

[READ MORE](#)

[SysAdmin Web Servers](#)

[How to Check CPU Utilization in Linux with Command Line](#)

March 6, 2024

Revision #1

Created 4 May 2024 14:09:44 by Administrador

Updated 16 May 2025 11:49:54 by Administrador